

Screen Recorder User Manual

Saltriver Info System Pvt. Ltd.

Screen Recorder User Manual

- **Introduction**

Screen Recorder Application is use to keep watch on desktop.

- **Features**

- It silently records computer screens at user defined interval time.
- Recorded screens can be viewed from website.

- **Prerequisites**

- Internet access must be available on each computer.

- **How it works?**

1. Create an Account on <http://www.mcameraapps.com> website.
2. Download and install Screen Recorder.

Download Setup from following location :


["http://saltriver.com/Upload/ScreenRecorder/Setup.zip"](http://saltriver.com/Upload/ScreenRecorder/Setup.zip).


Now install it on your computer.

Unzip Setup.zip and run the setup file "**ScreenRecorder.exe**" and follow the instructions.


It will automatically install JRE in your machine.


Now click on "**ScreenRecorder.exe**" it will shoe following window which shows the progress of installing JRE in your machine.





Click on **Accept** to install JRE.






It starts JRE installation.




Click on **Finish**




Click **OK** to start ScreenRecorder installation.




click on Next to continue installation.




Select installation directory and click Next or directly click on Next button to install it in default location.



Click on Install.





Click Finish to complete installation.

3. Configure your username and password and observation interval time.

Open ScreenRecorder folder from installation directory. Default location is "C:\Program Files\Saltriver\ScreenRecorder". Then open **UserDetails.dat** file and configure your username and password and observation interval.

As follows

```
USER_NAME=your_username  
USER_PASSWORD=your_password  
CAMERA_ID=1  
DELAY=10
```

4. Then launch Screen Recorder Application.
By executing ScreenRecorder.exe file from installation directory. It will shows following screen.



Click on "Trial" button if you want 30 days trial period of Screen Recorder Application.
Or Click on "Register" button if you want to register the Screen Recorder Application.
Or click on "Exit" button to close the application.

Trial Version

If you have selected Trial period in the first dialog box then when you start ScreenRecorder Application again it will show following dialog box.



Click on Continue button to continue with trial version or click on Register button to register ScreenRecorder Application.

Registered Version

How to register Screen recorder Application?

Click on "Register" button , it will show the following window.




Which shows Site Code for your machine. Give that site code and your scratch card number to provider and get a Authorization Key from provider. Enter Authorization key and click on register button. If Authorization key is valid then it starts ScreenRecorder Application in background and starts recording your desktop.


5. Monitor Recorded Screens.
Now you can monitor recorded screens from the website <http://www.mcameraapps.com> with same Username and Password information.
As follows

Open URL <http://www.mcameraapps.com> and login into your account

Screen Recorder – User Manual




Then it shows Welcome Page



Screen Recorder – User Manual

Click on **Current Image** from the left menu to view last recorded screen.



Click on **Stored Images** from the left menu to view all recorded screen shots.

Screen Recorder – User Manual

